



Clear Ballot

ClearVote 2.3
ClearAccess System
Identification Guide

ClearAccess System Identification Guide

Clear Ballot Part Number: 100038-10020

Copyright © 2012–2023 Clear Ballot Group. All rights reserved.

This document contains proprietary and confidential information consisting of trade secrets of a technical and commercial nature. The recipient may not share, copy, or reproduce its contents without express written permission from Clear Ballot Group.

ClearAccess, ClearAudit, Clear Ballot, ClearCast, ClearCount, ClearDesign, ClearVote and the Clear Ballot eye logo are registered trademarks, and CountServer, CountStation, DesignServer, DesignStation, ScanStation, Visualization of Voter Intent, Visual Verification, and Vote Visualization are trademarks of Clear Ballot Group. Other product and company names mentioned herein are the property of their respective owners.

Document Type: Customer

Clear Ballot Group
2 Oliver Street, Suite 200
Boston, MA 02109
857-250-4961
clearballot.com

Document history

Date	Description	Version	Authors
05/15/2017	Initial submission to EAC	1.0	Nel Finberg
06/16/2017	Minor updates for vote-by-mail campaign	1.0.1	Joni G. McNutt
01/19/2018	Vote-by-Mail campaign 2	1.0.2	Joni G. McNutt
01/31/2018	Updated with final file digest data for 1.4 EAC	1.0.3	Joni G. McNutt
02/21/2018	Updated cover for Vote-by-Mail campaign 2	1.0.4	Joni G. McNutt
04/27/2018	Minor edits	1.0.5	Mike Quigley
6/13/2018	Minor edits	1.0.6	Mike Quigley
8/15/2018	Revised instructions for verifying software. Added recommendation to use encrypted USB drives.	1.1	Mike Quigley
10/03/2018	Updated with final product and system files for 1.4.5	1.1.1	Joni G. McNutt
12/06/2018	Updated with final product and system files for 1.5	1.1.2	Joni G. McNutt
08/15/2019	Updated with final product and system files for 2.0	1.2	Joni G. McNutt
02/12/2020	Updated with final product and system files for 2.1	1.3	Joni G. McNutt
12/21/2020	Update product and system files for 2.2	1.4	George Petta
01/12/2021	Corrected the Clear Ballot Part Number	1.4.1	Joe Srednicki
09/17/2021	Update final product and system files for 2.2	1.4.2	Joe Srednicki
11/11/2021	Preliminary version for the 2.3 EAC application without software version numbers, file dates, and file digests.	1.5	Joe Srednicki
8/30/2022	Add product and system files for 2.3	1.6	Douglas McCulloch
03/21/2023	Updated "Installed third-party software." Made minor edits.	1.7	Erica Riddle, Kristina Arnold

Table of contents

Preface	5
Chapter 1. Verifying the ClearAccess software	6
1.1 Steps to verify the software	6
1.2 Installed ClearAccess product files	7
Chapter 2. Installed third-party software	8



Preface

This section defines the purpose of this document.

About this document

This document enables election officials to verify the software files for the ClearAccess system.

Scope of this document

This document contains the following chapters:

- Chapter 1. Verifying ClearAccess software
- Chapter 2. Installed third-party software

Intended audience

This document is for election officials and election staff who are responsible for operations and maintenance before, during, and after an election. Clear Ballot personnel also use this document to support election officials and election staff.

References to ClearVote products

A ClearVote® system can comprise the ClearAccess®, ClearCast®, ClearCount®, and ClearDesign® products. Jurisdictions are not required to purchase all products. You can ignore references to any ClearVote products that are not part of your voting system. Also ignore implementation options that are not relevant to your policies and procedures.

Contact us

Clear Ballot Group welcomes your feedback on our documentation. Please send comments to Documentation@ClearBallot.com.

If you have questions about using your product, contact your Clear Ballot representative.



Chapter 1. Verifying the ClearAccess software

After installing your ClearAccess software, you need to verify that the SHA-256 hash values of the installed software match those of the certified version. This process ensures that a third party or malware has not changed the contents of the software.

1.1 Steps to verify the software

To verify the installed software:

1. At the ClearAccess station, log in to Windows as the ClearAccess user.
The ClearAccess program starts and displays the login screen.
2. Log in with the administrator role and password.
3. Insert a USB drive into one of the available USB ports on the ClearAccess station.
4. Click **About**.
ClearAccess displays the About page.
5. Click the **Clear Ballot Product Files** tab and then click the **Export** button.
A message indicates that ClearAccess saved the product information as a CSV file on the USB drive
6. Click **OK** to close to close the message.
7. Close the About page and log out of the ClearAccess station.
8. Remove the USB drive from the ClearAccess station and insert it into another computer running Microsoft Windows.
Another computer is necessary because ClearAccess hardening prevents opening and viewing the file on the ClearAccess station.
9. Use a text or spreadsheet program, such as Notepad or Excel, to open and view the exported file.
10. Compare the hash values in the exported file to the hash values in Table 1-1 on page 7.
 - If the hash values match, the software is unmodified and matches the certified version.
 - If the hash values do not match, the software on the station does not match the certified version. The software has been modified, was improperly installed, or does not match for some other reason.
11. If a mismatch is found, do one of the following:
 - Follow procedures of your jurisdiction to resolve the discrepancy.
 - Contact Clear Ballot Technical Support for assistance (<https://clearballot.com/support>).

1.2 Installed ClearAccess product files

Table 1-1 lists the file specification, timestamp, and SHA-256 hash value for each of the Clear Ballot-authored files installed on the ClearAccess system.

Table 1-1. ClearAccess product files.

File	Date	File Digest
C:\Program Files (x86)\ClearBallot\ClearAccess\ClearAccess.exe	7/11/2022 11:03	acb4c33da24f5ebf4ca2d472365660426bf66504651a7e3bb9a14765cd98751d
C:\Program Files (x86)\ClearBallot\ClearAccess\Support\Zebra_CoreScanner_Driver_(64bit)_v3.07.0011\setup.iss	10/11/2021 15:45	c1474ba7da38ddffd2d4e1370143e94bd6a4f5b94f7a977320e933451fdd0ca6
C:\Program Files (x86)\ClearBallot\ClearAccess\Support\Zebra_CoreScanner_Driver_(64bit)_v3.07.0011\uninstall.iss	10/11/2021 15:46	0b161684d6d85d5850e6893d8bd4c640ffce0b7c98f504732a8513261708666a
C:\Program Files (x86)\ClearBallot\ClearAccess\Support\Zebra_CoreScanner_Driver_(64bit)_v3.07.0011\Zebra_CoreScanner_Driver_(64bit)_v3.07.0011.exe	10/7/2021 8:45	7c2ab40cc20b8126535d1ea07d2760b9b2f616053ed975e71ae861122d828944
C:\Program Files (x86)\ClearBallot\ClearAccess\uninstall.exe	8/27/2022 1:23	f52616faf6870887495329d1370516ec993654daed0807246b7e0c189021d6ac



Chapter 2. Installed third-party software

Table 2-1 lists the third-party software that is installed on the ClearAccess system. Clear Ballot does *not* modify any of the listed third-party software.

Table 2-1. Third-party software.

Package	Version	Description
ClearAccess	2.3.0	32-bit Clear Ballot Group Inc
Elo Touch Solutions. EloMultiTouch 6.8.0.19	6.8.0.19	64-bit Elo Touch Solutions, Inc.
Google Chrome	97.0.4692.99	64-bit Google LLC
Intel(R) Chipset Device Software	10.1.17861.8101	64-bit HIDDEN COMPONENT Intel Corporation
Intel(R) Chipset Device Software	10.1.17861.8101	32-bit Intel(R) Corporation
Intel(R) Processor Graphics	26.20.100.6913	32-bit Intel Corporation
Microsoft Visual C++ 2015-2019 Redistributable (x64) - 14.24.28127	14.24.28127.4	32-bit Microsoft Corporation
Microsoft Visual C++ 2019 X64 Additional Runtime - 14.24.28127	14.24.28127	64-bit HIDDEN COMPONENT Microsoft Corporation
Microsoft Visual C++ 2019 X64 Minimum Runtime - 14.24.28127	14.24.28127	64-bit HIDDEN COMPONENT Microsoft Corporation
Realtek High Definition Audio Driver	6.0.8734.1	32-bit Realtek Semiconductor Corp.
ST Microelectronics 3 Axis Digital Accelerometer Solution	4.22.0094	32-bit ST Microelectronics



Table 2-1. Third-party software. (continued)

Windows Driver Package - Zebra Technologies Inc. (WinUSB) WinUSB devices (03/31/2018 1.0.0.6)	03/31/2018 1.0.0.6	64-bit Zebra Technologies Inc.
Zebra CoreScanner Driver (64bit)	3.07.0011	64-bit HIDDEN COMPONENT Zebra Technologies
Zebra CoreScanner Driver (64bit)	3.07.0011	32-bit Zebra Technologies

